


# Blurred display of TightGate-Pro under Windows

Under Windows, the display of TightGate-Pro may be distorted on devices with a high DPI display. The problem is caused by automatic scaling under Windows. As the Windows operating system cannot scale the content of the TightGate-Viewernatively, the pixels are simply scaled, which causes the distorted display.


## The solution:

To rectify the distorted display under Windows, the scaling of the display should be carried out by TightGate-Viewer and not the Windows operating system. To set this, please proceed as follows:

1. Close the TightGate-Viewer.
2. Right-click on the application name (vncviewer.exe) in Explorer or in the Start menu or right-click on the desktop icon **Internet**. Select **Properties** and select the tab **Compatibility** tab and then select **Change high DPI settings** from.



3. Activate the checkbox **Override behaviour with high DPI scaling** checkbox and make sure that the scaling is set by the **application** is performed by the application.



4. Log in again at TightGate-Viewer, the distortion should no longer occur.

From:  
<https://help.m-privacy.de/> -

Permanent link:  
[https://help.m-privacy.de/doku.php/en:faq:tightgate\\_pro\\_dpi-werte](https://help.m-privacy.de/doku.php/en:faq:tightgate_pro_dpi-werte)

Last update: **2024/01/28 19:42**

